

# WhatsApp Business Cloud API - Groups Join Requests API | Developer Documentation

## WhatsApp Business Cloud API - Groups Join Requests API

Copy for LLM

[View as Markdown](#)

Version

The Groups API gives you simple functions to control groups through their lifecycle.

When you create a new group, an invite link is created for inviting participants to the group.

Since you cannot manually add participants to the group, simply send a message with your invite link to WhatsApp users who you would like to join the group.

---

Select language

---

---

### POST `/{Version}/{group_id}/join_requests`

Approve one or more join requests

#### Request Syntax

Try it

Select language

---

Select status code

---

Header Parameters

---

User-Agentstring

The user agent string identifying the client software making the request.

Authorizationstring·required

Bearer token for API authentication. This should be a valid access token obtained through the appropriate OAuth flow or system user token.

Content-TypeOne of "application/json", "application/x-www-form-urlencoded", "multipart/form-data"·required

Path Parameters

---

Versionstring·required

group\_idstring·required

Group ID

Required

---

Content Type: application/json

Schema: object

Show child attributes

---

messaging\_product"whatsapp"·required

---

join\_requestsarray of string·required

Array of join request IDs to approve

Show child attributes

---

join\_requests[]string

Join request ID

Responses

---

Approve one or more join requests

200

Join requests approval response

Content Type: application/json

Schema: object

Show child attributes

---

messaging\_productstring

---

approved\_join\_requestsarray of string  
Show child attributes

---

approved\_join\_requests[]string  
ID of approved join request

---

failed\_join\_requestsarray of object  
Show child attributes

---

failed\_join\_requests[]object  
Show child attributes

---

join\_request\_idstring

---

errorsarray of Error  
Show child attributes

---

errors[]Error  
Show child attributes

---

codeinteger  
Error code

---

messagestring  
Error message

---

titlestring  
Error title

---

error\_dataobject  
Show child attributes

---

detailsstring  
Error details

---

errorsarray of Error  
Show child attributes

---

errors[]Error  
Show child attributes

---

codeinteger  
Error code

---

messagestring  
Error message

---

titlestring  
Error title

---

error\_dataobject  
Show child attributes

---

detailsstring  
Error details  
Select language

---

Select status code

---

---

## DELETE

# / {Version} / {group\_id} / join\_requests

Reject one or more join requests

## Request Syntax

Try it  
Select language

---

Select status code

---

Header Parameters

---

User-Agentstring

The user agent string identifying the client software making the request.

Authorizationstring·required

Bearer token for API authentication. This should be a valid access token obtained through the appropriate OAuth flow or system user token.

Content-TypeOne of "application/json", "application/x-www-form-urlencoded", "multipart/form-data"·required

Path Parameters

---

Versionstring·required

group\_idstring·required

Group ID

Required

---

Content Type: application/json

Schema: object

Show child attributes

---

messaging\_product"whatsapp"·required

---

join\_requestsarray of string·required

Array of join request IDs to reject

Show child attributes

---

join\_requests[]string

Join request ID

Responses

---

Reject one or more join requests

200

Join requests rejection response

Content Type: application/json

Schema: object

Show child attributes

---

messaging\_productstring

---

rejected\_join\_requestsarray of string

Show child attributes

---

rejected\_join\_requests[]string

ID of rejected join request

---

failed\_join\_requestsarray of object  
Show child attributes

---

failed\_join\_requests[]object  
Show child attributes

---

join\_request\_idstring

---

errorsarray of Error  
Show child attributes

---

errors[]Error  
Show child attributes

---

codeinteger  
Error code

---

messagestring  
Error message

---

titlestring  
Error title

---

error\_dataobject  
Show child attributes

---

detailsstring  
Error details

---

errorsarray of Error  
Show child attributes

---

errors[]Error  
Show child attributes

---

codeinteger  
Error code

---

messagestring  
Error message

---

titlestring  
Error title

---

error\_dataobject  
Show child attributes

---

detailsstring  
Error details  
Select language

---

Select status code

---

## Authentication

Scheme	Type	Location
bearerAuth	HTTP Bearer	Header: Authorization

## Usage Examples

bearerAuth:

Include Authorization: Bearer your-token-here in request headers

## Global Authentication Requirements

All endpoints require:

bearerAuth

---

Revision #5

Created 2026-04-01 15:36:18 UTC by New Admin

Updated 2026-04-06 17:52:12 UTC by New Admin